

Code package for: “Spatio-Temporal Coupling Controlled Laser for Electron Acceleration (DOI : 10.1038/s42005-022-00954-8)”

Lu Wang

1 MIT License

Copyright (c) [2021] [Lu Wang] Email(no space): lu(dot)wangphysics(at)gmail(dot)com

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

2 Run the code

This code package should work on Linux, Unix and Windows system automatically. The standard CPU is sufficient. The code is tested on a single CPU on a standard PC (Intel(R) Core (TM) i5-10400 CPU @ 2.9 GHz) and the running time is < 60 s. To execute the code, open the main.m file and click run.

2.1 Choose the input electric field

The code has the possibilities to change the input electric field as standard pulse-front-tilt (PFT), direct incidence and the spatial-temporal-coupled (STC) scheme. This function can be realized by switching the command in the main.m file via the following:

```
1 case_name= 'tpf_standard_chirp';
```

means the input field chosen to be the standard PFT scheme,

```
1 case_name= 'direct';
```

means the direct incidence laser without any optical manipulation, and

```
1 case_name= 'tpf_stc_chirp';
```

means the input field is chosen to be the stc scheme.

2.2 Choose the calculation case

In the main.m file, the acceleration by the electric field is defined by:

```
1 NM=NM.init(my_cons,electron,E,case_name);
```

The perfectly matched pulse (the envelope calculation) is represented by

```
1 NM=NM.init(my_cons,electron,E,'Euler_matched');
```

2.3 Change parameters of the laser and electron

The optical pulse parameters can be changed in:"my_functions/optical_parameter_construct.m"

The electron parameters can be changed in:"my_functions/electron_properties_construct.m"

2.4 data process

The choice of saving the plotted figure/data can be set in the main.m line 11 as the following

```
1 save_flag=1;
```

, where '1' represents save the figures and '0' represents don't save anything. All the saved files can be found under my_output folder.

Enjoy life and happy coding. For any question please address to

```
1 Email(no space): lu(dot)wangphysics(at)gmail(dot)com
```